

Installation Guide

Module MPlayer


Installation

This plugin installs the standard way:

- 1. Unzip archive into the 'mod' directory of Moodle
- 2. Browse to administration notifications to finish installation.

Global settings

The global settings mostly deal with default values for many advanced parameters.



General settings

Player (technology)

Chooses the default technology used when creating a new instance. Both player may not provide exactly the same options, JW Player, f.e., natively is provided to play YouTube streams, but uses Flash technology. flowplayer is provided in html5 technology, but may not support adaptative bitrate.

Show debug code

Special feature for the full javascript API player setup (flowplayer). Displays the complete JS script for debugging prupose.

Teachers can choose

If enabled, the teacher in the course may be allowed to switch the player technology for the instance.

Width

Player expected width. Some external constraints such as theme or other layout situation may force this with not to be maintained.

the value should be compatible with a CSS width: attribute, in percent or pixels.

Height


Height, in pixels (no relative nor percent).

Skin (JWPlayer only)

the default skin of the JW player.

Show icons

Shows or hides video control commands and icons.



Control bar location

If player allows to, will change the location of the controls on the player interface.

Foreground color

If player allows to, changes the foreground color of the video GUI.

Background color

If player allows to, changes the background color of the video GUI, f.e. the background when no vido nor poster is playing.

Light color

If player allows to, changes the light color of the video GUI, tis usually afects the player control texts.

Autoplay

If enabled, new player instances will autoplay media as a default.

Full screen

If enabled, the full screen switch is available for users as a default for new instances.



Scaling content (JWPlayer)

Modes of image adjustement to outbounds of the player.

Volume

Default volume for new player instances.

Native full screen controls (flowplayer)

Some devices have some special behavious with the full screen feature. Usually those device provide a simulation of standard full-screen behaviour, rather than device native. If you experience some difficulties with the full screen among your users, this may help to fix some inadequate behaviours.

Extra Configuration with a streaming server

The MPlayer module can cooperate with a deferred video stream player. When feeding Moodle with videos, the media file is first upladed in moodle the standard way, then it is mooved to the remote storage and replaced locally by a manifest text file.

For this configuration to work, you will need locally mounting a remote volume from the media server filesystem.

Till now we worked in two opensource/community directions:

- Wowza server
- Apache pseudo-streaming using H264 additional module (https://www.apachehaus.net/modules/mod h264 streaming/)

HTTP media server	Default: Empty
HTTP media path mplayer httpmediapath	Default: Empty
HTTP storage dir rer httpmediacontentdir	Default: Empty
IP Streaming source mplayer wowzaserver	Default: Empty
treaming application layer wowzaapplication	/vod Default: /vod
Content Directory	Default: Empty

HTTP Pseudo streaming parameters

Server url

Main domain for the HTTP access to media .mp4

Relative media path

Relative media path. this will be append to the server URL.

HTTP Storage dir

Give the local mount path for the remote storage volume. this needs to be an absolute path in your local system (mount point).

Wowza parameters

Media flow server url

The rtmp url of the flow server. In case the server exploits HLS (over HTTP) or is using an H264 over apache distribution, this setting is not relevant.

Stream server application

Many streaming server propose several applications: VOD (video ondemand) is the standard application when reading a stored video, and live streaming when the stream comes from an active camera.

Remote media storage (wowza)

Give the local mount path for the remote storage volume. this needs to be an absolute path in your local system (mount point).

Return to the component index

Back to common plugin index - Back to home

From:

https://docsen.activeprolearn.com/ - Moodle ActiveProLearn Documentation

Permanent link:

https://docsen.activeprolearn.com/doku.php?id=mod:mplayer:install&rev=1586250693

Last update: 2024/04/04 15:50

